MailTight - Blackberry LogicMail Configuration

LogicMail Configuration Guide for Blackberry Devices

Download LogicMail

LogicMail - Over The Air (OTA) Installation
Download Link - http://logicmail.org/ota/
Select Download

Select the application Icon

Select the application ICON - cont.

It might also appear in the Downloads Folder

New account setup

New acount setup screen will appear

New account setup

MailTight

Your name:

Joe Smith

Name that appears in the From field of email messages
that you send

E-Mail address:

jsmith@mailtight.com

Account type:

● IMAP   ○ POP

Cancel   Next >

Account name: Joe Smith (this is you display name that will appear in the From field of email
messages that you send
E-Mail address: this is your actual email address.
Account type: Please select IMAP or POP
Press *Next* when complete

Incoming Mail Server Configuration

Incoming mail server

Use secure connection: **SSL** ▼

Port:
993

Username:
jsmith@mailtight.com

Password:
****

If blank, you will be prompted when connecting

Cancel   < Prev   Next >

Select: SSL
Port: 993 (default)
Username: this is your email address
Password: enter your password

Outgoing Mail Server Configuration

LogicMail - Outgoing (SMTP)
Account name: MailTight

Server: send.mailtight.com

Use secure connection: SSL ▾

Port: 465

Authentication: PLAIN ▾

Username: jsmith@mailtight.com
Password: **********

Connection method: Direct TCP ▾

☐ Use WiFi if available

Server: send.mailtight.com   (this is also known as the Outgoing mail server)
Use secure connection: SSL (default)
Port: 465 (default)
Authentication: PLAIN (default)
Username: this is your email address
Password: use the password supplied with your account

Connection method: Direct TCP - This is important, this allows for direct communication from the Blackberry to the MailTight servers without going via Blackberry e-mail servers

Miscellaneous

The following configration screen will appear.
Press *next*

Connection Settings

If this screen appears, you should check to see that Direct TCP is set.
It is highlighted as a red rectangle in this example.

Connection method: Direct TCP - This is important, this allows for direct communication from the Blackberry to the MailTight servers without going via Blackberry e-mail servers

Press *next*

Test Configuration

Test successful will be displayed.
If the test unsuccessful, please follow step
  - Connection Settings to ensure that **Direct TCP** is selected.

The Home screen will appear and the MailTight folders will appear under **MailTight (IMAP)**
This might take a few seconds while the inbox syncronises with the mail server

MailTight (IMAP) folder display

This screen will appear and the inbox folders will be displayed.
LogicMail is ready to use.